Kitty-Corner

CUT

• **Fabric A**

» Four 4-¾" squares

• **Fabric B**

» One 4-½" square

» Eight 2-¾" squares

» Eight 2-½" squares

• **Fabric C**

» Four 2-½" squares

• **Fabric D**

» Four 2-½" squares

Read through all instructions before beginning. Remove selvages. Cut pieces exactly as listed in instructions. Sew pieces right sides together and use an accurate ¼" seam allowance.

Quick-Corner Units

1. Draw a diagonal line on the wrong side of each 2-¾" fabric B square. Noting orientation of the drawn line, place a marked square right sides together on a corner of a 4-¾" fabric A square.


2. Sew on the line. Trim ¼" past the stitch line. Press corner open. Noting orientation of drawn line, repeat on the other corner as shown to make a Quick-Corner unit. Trim unit to 4-½" square, leaving a ¼" seam allowance on each side. Make a total of four Quick-Corner units.

Four-Patch Units

1. Noting placement, sew two 2-½" fabric B squares, one 2-½" fabric C square, and one 2-½" fabric D square into two rows of two squares each. Join rows to make a Four-Patch unit that measures 4-½" square. Make a total of four Four-Patch units.


BLOCK ASSEMBLY

1. Referring to the Block Assembly Diagram on page 2 and noting placement and orientation, sew one Quick-Corner unit between two Four-Patch units to make row A. Make a total of two A rows.

2. Sew the 4-½" fabric B square between two Quick-Corner units to make a B row.

3. Join the rows to make a block. Trim to 12-½" square.

Kitty-Corner Page 2

A

B

A

Block Assembly Diagram